



Copyright 2005-2008 Paragon Software (Smart Handheld Devices Division)

InterKey 3.0
for Windows Mobile

Dear customers!
Thank you for buying our software.
It is your interest that inspires us to develop innovative solutions for mobile devices.

Contents

CONTENTS	2
ABOUT	3
INTERKEY 3.0 EDITIONS.....	3
SYSTEM REQUIREMENTS	3
INSTALLATION	4
<i>From the Desktop PC</i>	4
<i>From CAB</i>	4
PURCHASE & REGISTRATION	5
<i>From Trial Reminder</i>	5
<i>From InterKey Options</i>	5
USING INTERKEY 3.0	6
<i>Getting Started</i>	6
<i>Selecting Layouts</i>	6
<i>Finger Input</i>	7
<i>Large and Small Keys</i>	7
<i>Using Gestures</i>	7
<i>Setting as Default Input Method</i>	8
<i>Word Completion</i>	8
REMOVING INTERKEY 3.0	9
CUSTOMER SUPPORT	9

About

InterKey 3.0 is an on-screen keyboard with a selection of language layouts, and smart functions such as Finger Input and Word Completion.

Languages supported are listed below. For some languages, more than one layout is available, for example, Latin American, Brazilian, US Dvorak, etc.

Multiple keyboard layouts may be used simultaneously.

Albanian	Czech	German	Macedonian	Serbian
Belarusian	Danish	Greek	Mongolian	Slovak
Belgian	Dutch	Hungarian	Norwegian	Slovenian
Bulgarian	English	Icelandic	Polish	Spanish
Canadian	Estonian	Italian	Portuguese	Swedish
Catalan	Finnish	Latvian	Romanian	Turkish
Croatian	French	Lithuanian	Russian	Ukrainian



InterKey 3.0 Editions

- **InterKey 3.0 Professional**
- **InterKey 3.0 Standard**, a compact version (does not include Word Completion).

System Requirements

InterKey 3.0 is developed for the following versions of Windows Mobile:
 Windows Mobile 6.1 Classic, Professional
 Windows Mobile 6 Classic, Professional
 Windows Mobile 5.0

NOTE: Earlier versions of Windows Mobile/PocketPC operating system are not supported in InterKey 3.0.

Installation

ATTENTION! To avoid the accidental loss of important data, it is recommended that you make a backup copy of your mobile device before installation.

If you have the previous version (**InterKey2.0**) installed, it will be removed before the new version is installed.

From the Desktop PC

NOTE: Check if the Microsoft ActiveSync is installed on your desktop PC. Otherwise you will need to install it first. Usually Microsoft ActiveSync is included on the Getting Started disk that comes with your Windows Mobile device.

The latest version of Microsoft ActiveSync can be downloaded from: www.microsoft.com

1. Connect your device to your desktop PC with a USB cable. (If you are running Microsoft ActiveSync for the first time, you do not need to synchronize your device with the PC).
2. When connected, double-click on the InterKey 3.0 *.exe.
3. Follow the instructions of the setup program.

NOTE: If you do not enter the registration code at this time, installation of a trial version may be continued. You can register your copy of the program later. See "Purchase & Registration" section for details.

Installation on the desktop PC is completed. On the mobile device screen:

4. Choose a location to install (if a storage card is inserted).

NOTE: InterKey is a system application and will be installed in the system folder irrespective of your choice. However, in case of InterKey 3.0 Professional, selecting Storage Card is recommended. This will save you over 3 MB of disk space as the word completion bases will be installed on the Storage Card.

5. Accept the terms of EULA.
6. Select keyboard layouts in the Layouts screen and press OK.
7. In InterKey 3.0 Professional Edition: A message will pop up suggesting that inactive word bases be deleted. (See "Using InterKey 3.0" section for details.). Press OK.

Installation complete!

From CAB



1. Download (copy) InterKey*.arm.cab to your mobile device and run it.
2. Complete steps 4-7 above.

Purchase & Registration

From Trial Reminder

While in trial mode, each time you turn on your device, a trial reminder will show prompting you to register or buy the program.

- Select **Buy** to order InterKey 3.0 online.
- If you already purchased the program and received a registration code, select **Register**.



- If you want to continue using a trial version, tap Ok to exit the window.

From InterKey Options

Go to **Start>Settings>System>InterKey Options>Registration**.


Select **Buy** to order InterKey 3.0 online.


To register the program, select **Register**. Enter the registration code received after purchase and press **Register**.

InterKey 3.0 can still be registered after the trial period (14 days) is over.

Using InterKey 3.0

Getting Started





Open an application and tap the  icon on the menu bar to display **InterKey Keyboard**.

If there is the default Windows Mobile keyboard icon on the menu bar, press the arrow button next to the icon and select **InterKey Keyboard** from the list of input methods


NOTE: If InterKey Keyboard cannot be selected, try setting it as default input method in *InterKey Options>Advanced*.

Selecting Layouts

Add/Remove layouts in **InterKey Options> Layouts** tab:



Finger Input



With InterKey 3.0, you can type using the finger as well as the stylus



By default, finger typing mode is on. Press a key and the selected key will be zoomed. Take your finger off the key to type the character on it. If a wrong key is zoomed, slide your finger on the screen releasing it when the desired key is displayed.

To turn off finger typing mode, go to **InterKey Options**> **Advanced** and uncheck **Zoom Key on tap** checkbox.

Large and Small Keys





By default, InterKey 3.0 uses finger-friendly layouts with large keys. Alternatively, there are normal Windows-style layouts with smaller keys.

To switch to normal keys, go to **InterKey Options**> **Advanced** and uncheck **Large Keys** checkbox.



Using Gestures

You can use the special keystrokes known as *gestures* for the following operations:

	Space	Add a white space
	Backspace	Erase the preceding character
	Shift+key	Capitalize a letter
	Enter	Go to new line


Gestures and finger typing are mutually incompatible functions. To use Gestures, go to **Options > Advanced**, uncheck *Zoom key on tap* checkbox and tick *Use Gestures*.

Setting as Default Input Method


InterKey Keyboard can be set as default input method, especially in case it turns out to be unselectable. Go to **InterKey Options > Advanced** and tick *Set as default input method* checkbox.

Word Completion


Word Completion allows faster typing of frequently used words. A new word, once entered, will be added to the word base.



Finger Input view



Standard view



Set your preferences for Word Completion in **InterKey Options>Word Completion**

To reduce the amount of storage used, it is recommended to delete word completion bases for those languages you are not likely ever to use.

NOTE: Word Completion is not available in InterKey 3.0 Standard.

Removing InterKey 3.0

1. Go to **Start>Settings>System>Remove programs**.
2. Select **Paragon Software InterKeyPPC** and tap **Remove**.
3. Tap **Yes** to confirm removal. Wait until the system completes uninstalling InterKey 3.0 and a reboot prompt appears. Tap **OK** to reboot.

Customer Support

Phone Support

+7 495 789-67-17 (Option 6), Monday - Friday from 11:00am to 7:00pm, Moscow Time

Online Support Request

Fill in our online form to have our Support Team representative contact you:

<http://www.penreader.com/support/index.html>

Support Knowledge Base:

<http://support.penreader.com>